

Chapter 2 - BASIC Language Vocabulary

This chapter is a reference to every word in BASIC. The words are listed in alphabetical order. Each entry shows the syntax form, a short description, and an example. Hardware-related keywords give the chapter where the screen, sound, or input system they belong to is described in full.

2.1 Notation

The following conventions appear throughout this chapter and the rest of the book:

Notation	Meaning
UPPERCASE	Type this word exactly.
<i>italics</i>	A piece of variable information you supply.
[...]	Optional. May be omitted.
[...]*	Optional and may be repeated.
a \ b	One of a or b.
<i>expr</i>	Any numeric expression.
<i>str-expr</i>	Any string expression.
<i>var</i>	A numeric variable name.
<i>str-var</i>	A string variable name (ends with \$).
<i>line</i>	A line number (0–4294967295).
<i>addr</i>	An integer expression interpreted as an address.

2.2 Direct-mode commands

These commands work only in direct mode. They are not part of the token table and may not appear inside a stored program line.

- **DIR** - list the names of files that BASIC can LOAD. See Chapter 34.

2.3 Alphabetical reference

ABS

ABS(*expr*)

Returns the absolute value of *expr*.

```
PRINT ABS(-5.5)
5.5
```

AHX

AHXargs

Play an AHX music file. See Chapter 18.

AND

exprANDexpr

Bitwise AND of two integers. Each operand is truncated to a signed 32-bit integer before the operation; the result is converted back to a number.

```
PRINT 12 AND 10
8
```

ANTIC

ANTICargs

Program the ANTIC display list. See Chapter 7.

ASC

ASC(str-expr)

Returns the byte value of the first character of *str-expr*. If the string is empty, returns 0. See Appendix C for the character code table.

```
PRINT ASC("A")
65
```

ATN

ATN(expr)

Returns the arctangent of *expr* in radians.

BIN\$

BIN\$(expr)

Returns the binary representation of the integer part of *expr* as a string of 0 and 1 digits.

```
PRINT BIN$(10)
1010
```

BITCLR

BITCLRaddr,bit

Clears bit *bit* (0–7) of the byte at *addr*. *bit* outside that range gives an unspecified result.

BITSET

BITSETaddr,bit

Sets bit *bit* (0–7) of the byte at *addr*.

BITTST

BITTST(*addr*,*bit*)

Returns -1 if bit *bit* (0–7) of the byte at *addr* is set, 0 if it is clear.

BLIT

BLIT*args*

Copy a block of pixels from one display region to another. See Chapter 4.

BLOAD

BLOAD*filename*,*addr*

Load a binary file into memory beginning at *addr*. Both arguments are required; omitting the comma and address loads nothing. See Chapter 34. BLOAD shares the token byte \$A3; LIST prints the byte as BLOAD.

BOX

BOX*x0*,*y0*,*x1*,*y1* [, *colour*]

Draw a rectangle. See Chapter 5.

CALL

CALL*addr*

Call IE64 machine code at *addr*. Returns to BASIC when the called code executes RTS. See Chapter 24 for the calling convention.

CHR\$

CHR\$(*expr*)

Returns a one-character string whose single byte equals the low eight bits of INT(*expr*). CHR\$(*n*) and CHR\$(*n*+256) produce the same string.

```
PRINT CHR$(65); CHR$(66); CHR$(67)
ABC
```

CIRCLE

CIRCLE*x*,*y*,*r* [, *colour*]

Draw a circle. See Chapter 5.

CLEAR

CLEAR

Reset all variables and arrays. Reset the DATA read pointer. Reset the GOSUB and structured-control stack. The program text is preserved.

CLS

CLS

Clear the screen. See Chapter 5.

COLOR

COLORargs

Set the active drawing colour. See Chapter 3.

CONT

CONT

Resume execution after a STOP. Has no effect if there is no saved state.

COPPER

COPPERargs

Program the copper list. See Chapter 4.

COS

COS(*expr*)

Returns the cosine of *expr*, where *expr* is in radians.

COSTART

COSTARTargs

Start a coprocessor program. Not tokenised; recognised as a raw statement when the line runs. See Chapter 31.

COSTOP

COSTOPargs

Stop a coprocessor program. Not tokenised. See Chapter 31.

COWAIT

COWAITargs

Wait for a coprocessor to reach a synchronisation point. Not tokenised. See Chapter 31.

DATA

DATAitem [, item]*

Declare numeric or string constants for later use with READ. The items are stored as raw text from DATA to the end of the line or to the next colon, and parsed when READ consumes them.

```
10 DATA 1, 2, "HELLO", 3.5
20 READ A, B, C$, D
```

DEC

DEC*var*

Subtract 1 from *var*. Equivalent to LET*var*=*var*- 1, but a single token.

DEEK

DEEK(*addr*)

Read 16 bits at *addr* (unsigned). The high 16 bits of the result are zero.

DEF

DEF FN*name*(*var*) =*expr*

Define a user function with one parameter. The function is called later with FN*name*(*expr*). DEF and TROFF share the token byte \$97. When the byte stands alone (no FN follows), the statement handler treats it as TROFF. LIST always prints this byte as TROFF.

DIM

DIM*name*(*size*) [, *name*(*size* [, *size*])]

Declare a numeric array. *size* is the highest legal subscript; the array has *size* + 1 elements per dimension, indexed from 0. Only numeric arrays are supported. There is no string-array form.

```
DIM A(10), GRID(7,7)
```

DO

DO

Begin a structured loop. End the loop with LOOP UNTIL*condition* or LOOP WHILE*condition*. See **LOOP**.

DOKE

DOKE*addr*, *expr*

Write 16 bits at *addr*. *addr* may be any byte address; alignment is not required.

ELSE

IF*condition*THEN*then-part*ELSE*else-part*

Mark the alternative branch of an IF statement. See **IF**.

END

END

Stop the running program and return to direct mode. There is no saved state for CONT.

ENVELOPE

ENVELOPE*args*

Set a volume envelope. See Chapter 11.

EOR

*expr*EOR*expr*

Bitwise exclusive-OR of two integers.

```
PRINT 12 EOR 10
6
```

EXP

EXP(*expr*)

Returns *e* raised to the power *expr*.

FN

FN*name*(*expr*)

Call a user function defined with DEF FN.

FOR

FOR*var*=*start*TO*end*[STEP*step*]

Begin a numeric loop. *var* takes the value *start* on first entry. After each pass through the loop body, the matching NEXT adds *step* (default 1) to *var* and compares it with *end*. The loop ends when *var* passes *end*.

```
10 FOR I = 1 TO 10
20   PRINT I,
30 NEXT
40 PRINT
```

FRE

FRE(*expr*)

Returns the approximate number of bytes of free string heap. The argument is ignored; use FRE(0).

GATE

GATE*args*

Open or close a sound-channel gate. See Chapter 11.

GET

GET*var* | GET*str-var*

Read one character from the keyboard without waiting for RETURN. *var* receives the byte value; *str-var* receives the character as a one-byte string. If no key is available, *var* is 0 and *str-var* is the empty string.

GOSUB

GOSUB *line*

Call the subroutine starting at *line*. Execution resumes at the statement after the matching RETURN. Subroutines may call other subroutines.

GOTO

GOTO *line*

Branch to *line*. Execution continues at the first statement of that line.

GTIA

GTIA *args*

Program the GTIA. See Chapter 7.

HEX\$

HEX\$ (*expr*)

Returns the hexadecimal representation of INT (*expr*) as a string of uppercase hex digits.

```
PRINT HEX$(255)
FF
```

HOST

HOST *subverb*

Issue a HOST command. *subverb* is one of NET, UPDATE, REBOOT, POWEROFF, HELP. Not tokenised; recognised as a raw statement when the line runs. See Chapter 35.

IF

IF *condition* THEN *then-part* [ELSE *else-part*]

If *condition* is non-zero, execute *then-part*; otherwise execute *else-part* if present, or fall through. *then-part* may be a line number (equivalent to GOTO *line*) or a statement list.

```
10 INPUT N
20 IF N < 0 THEN PRINT "MINUS" ELSE PRINT "PLUS OR ZERO"
```

INC

INC *var*

Add 1 to *var*.

INPUT

INPUT [*prompt*;] *var* [, *var*]*

Print *prompt* (a quoted string) if present, then ?, then read values typed on the terminal. Values are separated by commas.

```
10 INPUT "WHAT IS YOUR NAME"; N$
20 PRINT "HELLO, "; N$
```

INT

INT(*expr*)

Returns the integer part of *expr*, truncated toward 0.

LCASE\$

LCASE\$(*str-expr*)

Returns *str-expr* with every uppercase letter replaced by its lowercase equivalent. Non-letter bytes are unchanged.

LEEK

LEEK(*addr*)

Read 32 bits at *addr*. Equivalent to PEEK(*addr*).

LEFT\$

LEFT\$(*str-expr*, *n*)

Returns the first *n* bytes of *str-expr*. If *n* is negative, raises ILLEGAL QUANTITY.

LEN

LEN(*str-expr*)

Returns the number of bytes in *str-expr*.

LET

[LET] *var*=*expr*

Assign *expr* to *var*. The LET keyword is optional.

LINE

LINE *x0*, *y0*, *x1*, *y1* [, *colour*]

Draw a line. See Chapter 5.

LIST

LIST

Print the whole stored program. Any arguments after LIST are ignored; BASIC always lists every line.

LOAD

LOAD *filename*

Load a program file. See Chapter 34.

LOCATE

LOCATE *row, col*

Move the text cursor. See Chapter 5.

LOG

LOG(*expr*)

Returns the natural logarithm of *expr*. *expr* must be positive.

LOKE

LOKE *addr, expr*

Write 32 bits at *addr*. *addr* must be a multiple of 4. Equivalent to POKE *addr, expr*.

LOOP

LOOP UNTIL *condition* | LOOP WHILE *condition*

End a DO block. LOOP UNTIL repeats until *condition* is non-zero; LOOP WHILE repeats while *condition* is non-zero.

```
10 N = 0
20 DO
30   N = N + 1
40   PRINT N
50 LOOP UNTIL N >= 5
```

MAX

MAX(*expr, expr*)

Returns the larger of the two arguments.

MID\$

MID\$(*str-expr, start[, len]*)

Returns *len* bytes of *str-expr* starting at position *start* (1-based). If *len* is omitted, returns the substring from *start* to the end.

MIN

MIN(*expr, expr*)

Returns the smaller of the two arguments.

NEW

NEW

Erase the program, all variables, and all arrays. After NEW, the program is empty.

NEXT

NEXT [*var*]

Mark the end of a FOR loop. *var* identifies which loop to close; if omitted, the innermost loop is used.

NOT

NOT*expr*

Bitwise complement of INT(*expr*) as a signed 32-bit integer.

NULL

There is no NULL keyword. The token byte \$92 is emitted only for the spelling TRON. The detokeniser also prints TRON. See TRON.

ON

ON*expr*GOTO*line1*[, *line2*]*

Branch to *line-N*, where *N* is INT(*expr*). *N* must be between 1 and the number of line numbers listed. If *N* is out of range, execution falls through.

ON*expr*GOSUB*line1*[, *line2*]*

Like the GOTO form but each branch is a subroutine call.

OR

*expr*OR*expr*

Bitwise OR of two integers.

PALETTE

PALETTE*args*

Set entries in the colour palette. See Chapter 3.

PEEK

PEEK(*addr*)

Returns the 32-bit value at *addr*. *addr* must be a multiple of 4.

PEEK8(*addr*)

Returns the byte value at *addr*. *addr* may be any byte address.

PI

The constant 3.141593. Use 2 * PI for a full turn, or use TWOPI.

PLOT

PLOT*x,y*[, *colour*]

Set a single pixel. See Chapter 5.

POKE

`POKE`*addr,expr*

Write 32 bits at *addr*. *addr* must be a multiple of 4. If the address is not aligned, BASIC reports ILLEGAL FUNCTION CALL.

`POKE8`*addr,expr*

Write the low byte of *expr* at *addr*. *addr* may be any byte address.

POKEY

`POKEY`*yargs*

Program the POKEY sound chip. See Chapter 17.

POS

`POS`(*expr*)

Returns the current cursor column (0-based). The argument is ignored. Use `POS(0)`.

PRINT

`PRINT` [*item*[*,*|*;* *item*]*[*;*]]`

Print zero or more items to the terminal. The separators have these effects:

Separator	Effect
<code>;</code>	No padding between items.
<code>,</code>	Insert one TAB byte (<code>CHR\$(9)</code>) between items.
trailing <code>;</code>	Suppress the closing newline.
trailing <code>,</code>	Insert one TAB byte; do not suppress the newline.

The single character `?` is recognised by the tokeniser as a short form of `PRINT`. `LIST` prints `PRINT`.

```
PRINT "A"; "B"; "C"
ABC
```

PSG

`PSG`*yargs*

Program the PSG sound chip. See Chapter 13.

READ

`READ`*var*[*,* *var*]*

Consume successive items from the program's `DATA` statements and assign them to *var*. Numeric variables get numeric items; string variables get string items. `RESTORE` resets the read pointer.

REM

REM*comment*

Everything from REM to the end of the line is a comment.

RESTORE

RESTORE

Reset the DATA read pointer to the first DATA item in the program.

RETURN

RETURN

End a GOSUB. Execution resumes at the statement after the GOSUB that called this subroutine.

RIGHT\$

RIGHT\$(*str-expr*, *n*)

Returns the last *n* bytes of *str-expr*.

RND

RND(*expr*)

Returns a pseudo-random number in the range [0, 1). A negative argument seeds the generator; otherwise the argument is ignored.

RUN

RUN

Run the stored program from the lowest-numbered line. Numeric line arguments are not parsed, so RUN 100 behaves like RUN and always restarts from the first stored line. RUN preserves variables and arrays; only the DATA pointer and the control stack are reset.

RUN "*filename*" is recognised as a direct-mode form by the prompt and hands off to external image execution (Chapter 34). It is not part of the BASIC keyword's own parser.

SADD

SADD(*str-var*)

Returns the address of the byte buffer that holds the current value of *str-var*. The address is invalidated by the next string allocation, so save the bytes you need before BASIC creates a new string.

SAP

SAP*args*

Play a SAP music file through the POKEY. See Chapter 17.

SAVE

SAVEfilename

Save the program to a file. See Chapter 34.

SCREEN

SCREENargs

Select a screen mode. See Chapter 5.

SCROLL

SCROLLargs

Scroll the screen. See Chapter 4.

SGN

SGN(expr)

Returns -1, 0, or +1 depending on the sign of *expr*.

SID

SIDargs

Program the SID sound chip. See Chapter 15.

SIN

SIN(expr)

Returns the sine of *expr*, in radians.

SOUND

SOUNDargs

Play a tone on a sound channel. See Chapter 11.

SQR

SQR(expr)

Returns the square root of *expr*. *expr* must not be negative.

STEP

See **FOR**.

STOP

STOP

Stop the program and save its position so that **CONT** can resume.

STR\$

STR\$(*expr*)

Returns the decimal string representation of *expr*. A leading space is reserved for the sign: a positive number has a leading space; a negative number has a leading -.

SWAP

SWAP*var*, *var*

Exchange the values of two variables. Both variables must be of the same type (both numeric or both string).

TAB

TAB(*expr*)

Used only inside a PRINT list. Prints spaces so that the cursor sits at column *expr* (counting from 0). Has no effect if the cursor has already passed *expr*.

TAN

TAN(*expr*)

Returns the tangent of *expr*, in radians.

TED

TED*args*

Program the TED chip (video and audio). See Chapter 6 and Chapter 16.

TEXTURE

TEXTURE*args*

Bind a texture for Voodoo rasterisation. See Chapter 9.

THEN

See **IF**.

TO

See **FOR**.

TRIANGLE

TRIANGLE*args*

Rasterise a Voodoo triangle. See Chapter 9. The word TRICOLOR is recognised in argument position by the Voodoo dispatcher; it is left as literal characters by the tokeniser.

TROFF

TROFF

Turn off line-by-line tracing. `TROFF` and `DEF` share the token byte \$97. The handler treats a bare \$97 (no `FN` follows) as `TROFF`. `LIST` always prints this byte as `TROFF`, even if you typed `DEF`.

TRON

`TRON`

Turn on line-by-line tracing. While tracing is on, each line number is printed before its statements run.

TWOPI

The constant 6.283185 (two times π).

UCASE\$

`UCASE$(str-expr)`

Returns *str-expr* with every lowercase letter replaced by its uppercase equivalent. Non-letter bytes are unchanged.

ULA

`ULAargs`

Program the ULA display. See Chapter 8.

UNTIL

See **LOOP**.

USR

`USR(addr)`

Call IE64 machine code at *addr*. The routine returns an integer value through the result register; `USR` returns that value as a number. See Chapter 24 for the calling convention.

VAL

`VAL(str-expr)`

Parse *str-expr* as a number. Stops at the first character that is not part of a numeric literal.

```
PRINT VAL("3.14XYZ")
3.14
```

VARPTR

`VARPTR(var)`

Returns the address of the storage slot that holds the value of *var*. The slot is four bytes wide.

VERTEX

`VERTEXargs`

Submit a Voodoo vertex. See Chapter 9.

VOODOO

VOODOO*args*

Program the Voodoo rasteriser. See Chapter 9.

VSYNC

VSYN*Cargs*

Wait for vertical retrace. See Chapter 3.

WAIT

WAIT*addr,mask[,xor]*

Read the 32-bit value at *addr* repeatedly until ((*value* EOR*xor*) AND*mask*) is non-zero. *xor* defaults to 0. WAIT returns after approximately one million polls if the condition is never met.

```
REM Wait until bit 0 of the keyboard status is set
WAIT &H00100004, 1
```

WEND

WEND

Alternate spelling of UNTIL when terminating a WHILE loop. WEND and UNTIL share the same token byte (\$AF); LIST prints this byte as UNTIL.

WHILE

WHILE*condition*

Begin a loop that runs while *condition* is non-zero. The loop body runs until a matching LOOP UNTIL or LOOP WHILE. See LOOP.

WIDTH

WIDTH is the internal name for token \$A3. The tokeniser does not recognise the spelling WIDTH; use BLOAD. See BLOAD.

XOR

There is no XOR keyword in this BASIC. The exclusive-OR operator is EOR.

ZBUFFER

ZBUFFER*args*

Enable or configure the Voodoo Z-buffer. See Chapter 9.

2.4 Operator symbols

Every operator is described at its alphabetical position above. The operator symbols are summarised here for quick reference. See Chapter 1 §1.8 for the precedence table.

Symbol	Keyword name
+	(add)
-	(subtract or unary minus)
*	(multiply)
/	(divide)
^	(power)
<<	LSHIFT
>>	RSHIFT
<	LT
<=	(LT followed by =)
=	EQUAL
<>	(LT followed by >)
>	GT
>=	(GT followed by =)
?	PRINT (alternate spelling)

2.5 Cross-reference index

The hardware-related keywords above point at the chapter that documents the underlying device in full. The list below collects those references:

Keyword	Chapter
SCREEN, CLS, PLOT, LINE, CIRCLE, BOX, LOCATE	5
PALETTE, VSYNC, COLOR	3
SCROLL, COPPER, BLIT	4
TED	6 (video), 16 (audio)
ANTIC, GTIA	7
ULA	8
VOODOO, ZBUFFER, VERTEX, TRIANGLE, TEXTURE	9
SOUND, ENVELOPE, GATE	11
PSG	13
SID	15
POKEY, SAP	17
AHX	18
HOST	35
COSTART, COSTOP, COWAIT	31
CALL, USR	24

Keyword	Chapter
LOAD, SAVE, BLOAD, RUN ".ie"	34